

# Bindem™

## UTILITY MODIFIER

Bindem™ is a utility modifier used to improve physical tank mix compatibility in herbicide tank mixes.

### WHY USE BINDEM™ UTILITY MODIFIER?

- Bindem is a utility modifier that improves the physical compatibility of certain grass and broadleaf herbicide tank mixes.
- Bindem must be used with Simplicity™ GoDRI™ herbicide and broadleaf herbicide tank mixes.
- 1 x 4.8 L jug of Bindem treats 80 acres, regardless of water volume used.
- Bindem was launched as a component of the Tridem 40 acre case and the Tridem™ herbicide 240 acre bulk pallet in 2019.
- Bindem is also offered as a stand alone product (4 x 4.8 L case).
- When using Simplicity™ GoDRI™ at the full rate, a 4.8 L jug of Bindem treats the same acres as a 2.24 kg jug of Simplicity GoDRI.

### APPLICATION GUIDELINES

<b>PRODUCTS</b> Simplicity™ GoDRI™ Tridem™ (Bindem included in co-pack)	<b>PACKAGING</b> <ul style="list-style-type: none"> <li>• Bindem: 4 x 4.8 L case</li> <li>• Tridem 40 acre case: 1 x 2.4 L jug</li> <li>• Tridem 240 bulk unit: 2 x 7.1 L jugs</li> </ul>
	<b>RATES</b> <p>60 ml/ac</p>
	<b>ACRES TREATED</b> <ul style="list-style-type: none"> <li>• Each 4.8 L jug treats 80 acres</li> <li>• Each 2.4 L jug treats 40 acres</li> <li>• Each 7.1 L jug treats 120 acres</li> </ul>

#### SIMPLICITY GODRI + BINDEM MIXING INSTRUCTIONS

1. Fill the spray tank with ½ to ¾ of the required amount of water
2. Continue agitation throughout the mixing and spraying procedure
3. Add any broadleaf tank mix partners that are a dry formulation
4. Add the required amount of Simplicity GoDRI
5. Add the required amount of liquid broadleaf tank mix partner
6. Add the required amount of Bindem utility modifier
7. Complete filling the sprayer tank with water

#### TRIDEM + BINDEM MIXING INSTRUCTIONS

1. Fill sprayer tank ½ to ¾ full of water
2. Continue agitation throughout the mixing and spraying procedure
3. Add the required amount of Tridem A Herbicide
4. Add the required amount of Tridem B Herbicide and continue to agitate
5. Add 2,4-D Ester 700 next and continue agitation
6. Add the required amount of Bindem utility modifier
7. Complete filling the sprayer tank with water